





Routing Protocols and Concepts – Chapter 5

Cisco | Networking Academy® | Mind Wide Open®

Objectives


- Describe the functions, characteristics, and operation of the RIPv1 protocol.
- Configure a device for using RIPv1.
- Verify proper RIPv1 operation.
- Describe how RIPv1 performs automatic summarization.
- Configure, verify, and troubleshoot default routes propagated in a routed network implementing RIPv1.
- Use recommended techniques to solve problems related to RIPv1



- RIP Characteristics
 - -A classful, Distance Vector (DV) routing protocol
 - -Metric = hop count
 - -Routes with a hop count > 15 are unreachable
 - -Updates are broadcast every 30 seconds



- RIP Message Format
- RIP header divided into 3 fields
 - -Command field
 - -Version field
 - -Must be zero
- Route Entry composed of 3 fields
 - -Address family identifier
 - -IP address
 - -Metric



sending out message.

IP Address

Metric

The address of the destination route, which may be a network, subnet, or

Hop count between 1 and 16. Sending router increases the metric before

- RIP Operation
 - -RIP uses 2 message types:
 - Request message
 - -This is sent out on startup by each RIP enabled interface
 - -Requests all RIP enabled neighbors to send routing table
 - Response message
 - -Message sent to requesting router containing routing table



IP addresses initially divided into classes

-Class A

-Class B

-Class C

- RIP is a classful routing protocol
 - -Does not send subnet masks in routing updates

Default Subnet Masks for Address Classes

8 bits	8 bits	8 bits	8 bits
Network	Host	Host	Host
255 .	0	. 0	. 0

	Network	Network	Host	Host	
Ī	255	255	0	 0	

Network	Network	Network	L	Host
255	255	255		0

Class A Address Range: 1.0.0.0 to 126.255.255.255 Class B Address Range: 128.0.0.0 to 191.255.255.255 Class C Address Range: 192.0.0.0 to 223.255.255.255

Class A:

Class B:


Class C:



Administrative Distance

-RIP's default administrative distance is 120

Verifying Administrative Distance




```
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
      N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
      E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
      i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
      * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route
Gateway of last resort is not set
    192.168.1.0/24 [120/1] via 192.168.6.2, 00:00:05, Serial0/0/0
   192.168.2.0/24 [120/1] via 192.168.6.2, 00:00:05, Serial0/0/0
                    [120/1] via 192.168.4.2, 00:00:05, Serial0/0/1
    192.168.3.0/24 [120/1] via 192.168.4.2, 00:00:05, Serial0/0/1
   192.168.4.0/24 is directly connected, Serial0/0/1
    192.168.5.0/24 is directly connected, FastEthernet0/0
    192.168.6.0/24 is directly connected, Serial0/0/0
```

```
R3#show ip protocols
Routing Protocol is "rip"
  <output omitted>
  Redistributing: rip
  Default version control: send version 1, receive any version
                          Send Recv Triggered RIP Key-chain
    Interface
    FastEthernet0/0
                               1 2
                               1 2
    Seria10/0/0
    Seria10/0/1
                                1 2
  Automatic network summarization is in effect
  Routing for Networks:
   192,168,4.0
    192.168.5.0
    192.168.6.0
  Routing Information Sources:
    Gateway
                    Distance
                                  Last Update
    192.168.6.2
                         120
                                  00:00:10
                         120
    192.168.4.2
                                  00:00:18
  Distance: (default is 120)
```

Basic RIPv1 Configuration

- A typical topology suitable for use by RIPv1 includes:
 - -Three router set up
 - -No PCs attached to LANs
 - -Use of 5 different IP subnets



RIP Topology: Scenario A

Addressing Table: Scenario A

Device	Inferface	IP Address	Subnet Mask
R1	Fa0/0	192.168.1.1	255.255.255.0
KI	S0/0/0	192.168.2.1	255.255.255.0
	Fa0/0	192.168.3.1	255.255.255.0
R2	S0/0/0	192.168.2.2	255.255.255.0
	S0/0/1	192.168.4.2	255.255.255.0
D2	Fa0/0	192.168.5.1	255.255.255.0
R3	S0/0/1	192.168.4.1	255.255.255.0

192.168.1.0/24

Basic RIPv1 Configuration

- Router RIP Command
 - -To enable RIP enter:
 - -Router rip at the global configuration prompt
 - -Prompt will look like *R1(config-router)*#


```
R1#conf t
Enter configuration commands, one per line. End with CTRL/Z.
R1(config) #router ?
            Border Gateway Protocol (BGP)
  pab
            Exterior Gateway Protocol (EGP)
            Enhanced Interior Gateway Protocol (EIRGP)
  eigrp
  igrp
            Interior Gateway Routing Protocol (IGRP)
  isis
            ISO IS-IS
  iso-igrp IGRP for OSI networks
  mobile
            Mobile routes
  odr
            On Demand stub Routes
  ospf
            Open Shortest Path First (OSPF)
            Routing Information Protocol (RIP)
  rip
R1(config) #router rip
R1(config-router)#
```

illiili cisco.



Basic RIPv1 Configuration

- Specifying Networks
 - -Use the *network* command to:
 - -Enable RIP on all interfaces that belong to this network
 - -Advertise this network in RIP updates sent to other routers every 30 seconds




```
R1(config) #router rip
R1(config-router) #network 192.168.1.0
R1(config-router) #network 192.168.2.0
```

```
R2(config) #router rip
R2(config-router) #network 192.168.2.0
R2(config-router) #network 192.168.3.0
R2(config-router) #network 192.168.4.0
```

```
R3(config)#router rip
R3(config-router)#network 192.168.4.0
R3(config-router)#network 192.168.5.0
```



- Show ip Route
- To verify and troubleshoot routing
 - -Use the following
 - commands:
 - -show ip route
 - -show ip protocols
 - -debug ip rip



R 192.168.5.0/24 [120/2] via 192.168.2.2, 00:00:23, Serial 0/0/0

ın	terpreting a RIP Route in the Routing Table
R	Identifies the source of the route as RIP.
192.168.5.0	Indicates the address of the remote network.
/24	The subnet mask used for this network
[120/2]	The administrative distance (120) and the metric (2 hops)
via 192.168.2.2	Specifies the address of the next-hop router (R2) to send traffic to for the remote network.
00:00:23	Specifies the amount of time since the route was updated (here, 23 seconds). Another update is due in 7 seconds.
SerialO/O/O	192.168.4.2



show ip protocols command

-Displays routing protocol configured on router

```
R2#show ip protocols
Routing Protocol is "rip"
  Sending updates every 30 seconds, next due in 23 seconds
  Invalid after 180 seconds, hold down 180, flushed after 240
  Outgoing update filter list for all interfaces is not set
   Incoming update filter list for all interfaces is not set
   Redistributing: rip
  Default version control: send version 1, receive any version
    Interface
                                   Send Recv Triggered RIP Key-chain
    FastEthernet0/0
                                             1 2
    Seria10/0/0
                                             1 2
    Serial0/0/1
                                             1 2
   Automatic network summarization is in effect
   Maximum path: 4
  Routing for Networks:
    192.168.2.0
    192,168,3.0
    192,168,4.0
  Routing Information Sources:
    Gateway
                      Distance
                                      Last Update
    192.168.2.1
                                         00:00:18
    192.168.4.1
                            120
                                         00:00:22
  Distance: (default is 120)
Shows which routing processes are enabled
Timers currently in use including when the next
update will be sent out by this router (23 seconds)
  CCNP-level topics include:
   Filtering what updates this router will send and receive
   Redistributing: rip means that this router is sending and receiving only RIP
   Shows which interfaces are currently sending and receiving
   RIP updates as well as which RIP version.
      Automatic summarization in effect means this router is summarizing to the classful network boundary.
      Maximum paths specifies how many equal-cost routes RIP will use to send traffic to the same destination.
         Routing for Networks displays the classful network address configured in RIP.
         router configuration mode.


    Routing Information Sources are the RIP neighbors this router is currently receiving updates from.

          Includes next-hop IP address, the AD, and when the last update was received.
          Last line shows the AD for this router.
```



Debug ip rip command

-Used to display RIP routing updates as they are happening



```
R2#debug ip rip
RIP protocol debugging is on
RIP: received v1 update from 192,168,2,1 on Seria10/0/0 - R2 receives an update from R1 advertising the R1's directly connected LAN.
      192.168.1.0 in 1 hops
RIP: received v1 update from 192.168.4.1 on Seria10/0/1 - R2 receives an update from R3 advertising the R3's directly connected LAN.
      192.168.5.0 in 1 hops
RIP: sending v1 update to 255.255.255.255 via FastEthernet0/0 (192.168.3.1)
RIP: build update entries
                                               R2 sends an update out Fa0/0 to all networks in the routing table except the network attached
      network 192.168.1.0 metric 2
                                               to Fa0/0.
      network 192.168.2.0 metric 1
      network 192,168,4,0 metric 1
      network 192.168.5.0 metric 2
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (192.168.4.2)
RIP: build update entries
                                              R2 sends an update out S0/0/1 to R3. Included in the update are R1's LAN, the WAN between R1
      network 192.168.1.0 metric 2
                                              and R2, and R2's LAN.
      network 192.168.2.0 metric 1
                                              Note that split horizon is in effect. R2 does not advertise the R3 LAN back to R3.
      network 192.168.3.0 metric 1
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (192.168.2.2)
RIP: build update entries
```

- Passive interface command
 - -Used to prevent a router from sending updates through an interface
 - -Example:

Router(config-router)#passive-interface interface-type interface-number



Passive interfaces

```
R2(config) #router rip
R2(config-router) #passive-interface FastEthernet 0/0
R2(config-router) #end
R2#show ip protocols
Routing Protocol is "rip"
    Sending updates every 30 seconds, next due in 14 seconds
    Invalid after 180 seconds, hold down 180, flushed after 240
   Outgoing update filter list for all interfaces is
    Incoming update filter list for all interfaces is
   Redistributing: rip
    Default version control: send version 1, receive any version
                             Send Recv Triggered RIP Key-chain
       Serial0/0/0
                                   1 2
       Serial0/0/1
                                   1 2
   Automatic network summarization is in effect
    Routing for Networks:
       192.168.2.0
       192.168.3.0
       192.168.3.0
       192.168.4.0
    Passive Interface(s):
       FastEthernet0/0
   Routing Information Sources:
                   Distance
    Gateway
                                  Last Update
      192.168.2.1
                           120
                                    00:00:27
      192.168.4.1
                           120
                                    00:00:23
Distance: (default is 120)
```

Notice FastEthernet 0/0 is no longer listed under "Default version contol:"

However, R2 is still routing for 192.168.3.0 and now lists FastEthernet under "Passive Interfaces:"



Modified Topology

The original scenario has been modified such that:

Three classful networks are used:

172.30.0.0/16

192.168.4.0/24

192.168.5.0/24

The 172.30.0.0/16 network is subnetted into three subnets:


172.30.1.0/24

172.30.2.0/24

172.30.3.0/24

The following devices are part of the 172.30.0.0/16 classful network address:

All interfaces on R1 S0/0/0 and Fa0/0 on R2



Subnet Masl Subnet Mask Subnet Mask 255.255.255.0 Fa0/0 172.30.1.1 R1 \$0/0/0 172.30.2.1 255.255.255.0 Fa0/0 172.30.3.1 255.255.255.0 R2 S0/0/0 172.30.2.2 255.255.255.0 S0/0/1 192.168.4.9 255.255.255.252 Fa0/0 192,168,5,1 255,255,255,0 R3 S0/0/1 192.168.4.10 255.255.255.252



Configuration Details

-To remove the RIP routing process use the following command

No router rip


-To check the configuration use the following command


Show run

```
R2(config)#interface S0/0/0
R2(config-if) #ip address 172.30.2.2 255.255.255.0
R2(config-if)#interface fa0/0
R2(config-if) #ip address 172.30.3.1 255.255.255.0
R2(config-if)#interface S0/0/1
R2(config-if) #ip address 192.168.4.9 255.255.255.252
R2(config-if) #no router rip
R2(config) #router rip
R2 (config-router) #network 172.30.0.0
R2(config-router)#netowrk 192.168.4.8
R2(config-router) #passive-interface FastEthernet 0/0
R2(config-router)#end
R2#show run
<output omitted>
router rip
 passive-interface FastEthernet0/0
```



- Boundary Routers
 - -RIP automatically summarizes classful networks
 - -Boundary routers summarize RIP subnets from one major network to another.








Processing RIP Updates

- 2 rules govern RIPv1 updates:
 - -If a routing update and the interface it's received on belong to the **same** network then

The subnet mask of the interface is applied to the network in the routing update

-If a routing update and the interface it's received on belong to a **different** network then

The classful subnet mask of the network is applied to the network in the routing update.



Sending RIP Updates


-RIP uses automatic summarization to reduce the

size of a routing table.


```
R1#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       <remaining codes omitted>
Gateway of last resort is not set
     172.30.0.0/24 is subnetted, 3 subnets
       172.30.1.0 is directly connected, FastEthernet0/0
       172.30.2.0 is directly connected, Serial0/0/0
       172.30.3.0 [120/1] via 172.30.2.2, 00:00:17, Serial0/0/0
    192.168.4.0/24 [120/1] via 172.30.2.2, 00:00:17, Serial0/0/0
    192.168.5.0/24 [120/2] via 172.30.2.2, 00:00:17, Serial0/0/0
R2#debug ip rip
RIP protocol debugging is on
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (172.30.2.2)
RIP: build update entries
      network 172.30.3.0 metric 1
      network 192.168.4.0 metric 1
     network 192.168.5.0 metric 2
RIP: sending v1 update to 255.255.255.255 via Serial0/0/1 (192.168.4.9)
RIP: build update entries
      network 172.30.0.0 metric 1
R2#undebug all
All possible debugging has been turned off
Routes sent to R1.
R3#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
      <remaining codes omitted>
Gateway of last resort is not set
     172.30.0.0/16 [120/1] via 192.168.4.9, 00:00:15, Serial0/0/1
     192.168.4.0/30 is subnetted, 1 subnets
       192.168.4.8 is directly connected, Serial0/0/1
     192.168.5.0/24 is directly connected, FastEthernet0/0
 Compare R1 and R3 Routes for Network 172.30.0.0
```



- Advantages of automatic summarization:
 - -The size of routing updates is reduced
 - -Single routes are used to represent multiple routes which results in faster lookup in the routing table.




- Disadvantage of Automatic Summarization:
 - -Does not support discontiguous networks



Subnet Mask	Subnet Mask	Subnet Mask	Subnet Mask
	Fa0/0	172.30.1.1	255.255.255.0
R1	Fa0/1	172.30.2.1	255.255.255.0
	S0/0/0	209.165.200.229	255.255.255.252
	Fa0/0	10.1.0.1	255.255.255.0
R2	S0/0/0	209.165.200.230	255.255.255.252
	S0/0/1	209.165.200.233	255.255.255.252
	Fa0/0	172.30.100.1	255.255.255.0
R3	Fa0/0	172.30.200.1	255.255.255.0
	S0/0/1	209.165.200.234	255.255.255.252

- Discontiguous
 Topologies do not
 converge with RIPv1
- A router will only advertise major network addresses out interfaces that do not belong to the advertised route.







Default Route and RIPv1

- Modified Topology: Scenario C
- Default routes


Packets that are not defined specifically in a routing table will go to the specified interface for the default route

Example: Customer routers use default routes to connect to an ISP router.

Command used to configure a default route is ip route 0.0.0.0 0.0.0.0 s0/0/1



Default Route and RIPv1



Propagating a Default Route with default-information originate

- · Disable RIP routing on R2 for the 192,168.4.0 network only.
- · Configure R2 with a default route pointing to R3.

R2(config) Frouter rip

R2(config-router) #no network 192.168.4.0

R2(config=router) #exit

R2(config)#ip route 0.0.0.0 0.0.0.0 serial 0/0/1

- · Completely disable RIP routing on R3.
- · Configure R3 with a static route pointing R2.

R3(config) #no router rip R3(config) #ip route 172.30.0.0 255.255.252.0 serial 0/0/1

Gateway of last resort is not set

172.30.0.0/24 is subnetted, 3 subnets

172.30.1.0 is directly connected, FastEthernetO/O

172.30.2.0 is directly connected, SerialO/O/O

172.30.3.0 [120/1] via 172.30.2.2, 00:00:05, Serial0/0/0

R2fehow ip route

Gateway of last resort is 0.0.0.0 to network 0.0.0.0

172.30.0.0/24 is subnetted, 3 subnets

172.30.1.0 [120/1] via 172.30.2.1, 00:00:03, Serial0/0/0

172.30.2.0 is directly connected, SerialO/O/O

172.30.3.0 is directly connected, FastEthernet0/0

192.168.4.0/30 is subnetted, 1 subnets

192.168.4.8 is directly connected, Serial0/0/1

0.0.0.0/0 is directly connected, SerialO/0/1

R3#show ip route

Gateway of last resort is not set

172.30.0.0/22 is subnetted, 1 subnets

172.30.0.0 is directly connected, SerialO/0/1

192.168.4.0/30 is subnetted, 1 subnets

192.168.4.8 is directly connected, Serial0/0/1

192.168.5.0/24 is directly connected, FastEthernet0/0

Default Route and RIPv1

- Propagating the Default Route in RIPv1
- Default-information originate command

-This command is used to specify that the router is to originate default information, by propagating the static default route in RIP update.

```
172.168.3.0/24
   Propagating a Default with default-information originate
                                                 RIP
                                                                             192.168.4.8/30
                                        172.130.2.0/24
                                                                            Route
                                                                               Fa0/0
                                                                                          192.168.5.0/24
                        172.168.1.0/24
R2(config) #router rip
R2 (config-router) #default-information originate
R2(config-router)#end
R2#debug ip rip
RIP protocol debugging is on
RIP: sending v1 update to 255.255.255.255 via Serial0/0/0 (172.30.2.2)
RIP: build update entries
           subnet 0.0.0.0 metric 1
                                             Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B- BGP
           subnet 172.30.3.0 metric 2
                                                     D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
R2#undebug all
                                                     N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
All possible debugging has been turned off
                                                     E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
                                                     i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
 R2 is now sending a "quad-zero" route to R1
                                                     * - candidate default, U - per-user static route, o - ODR
                                                     P - periodic downloaded static route
                                              Gateway of last resort is 172.30.2.2 to network 0.0.0.0
                                                 172.30.0.0/24 is subnetted, 3 subnets
                                                172.30.2.0 is directly connected, Serial0/0/0
                                                172.30.3.0 [120/1] via 172.30.2.2 00:00:16, Serial0/0/0
                                                172.30.1.0 is directly connected, Fast Ethernet0/0
                                              R* 0.0.0.0/0 [120/1] via 172.30.2.2, 00:00:16, Serial0/0/0
                                               R1 has a "gateway of last resort", a candidate default route.
```

Summary

RIP characteristics include:

Classful, distance vector routing protocol

Metric is Hop Count

Does not support VLSM or discontiguous subnets

Updates every 30 seconds

Rip messages are encapsulated in a UDP segment with source and destination ports of 520



Summary: Commands used by RIP

Command	Command's purpose
Rtr(config)#router rip	Enables RIP routing process
Rtr(config-router)#network	Associates a network with a RIP routing process
Rtr#debug ip rip	used to view real time RIP routing updates
Rtr(config-router)#passive-interface fa0/0	Prevent RIP updates from going out an interface
Rtr(config-router)#default-information originate	Used by RIP to propagate default routes
Rtr#show ip protocols	Used to display timers used by RIP

